

CONTENTS

Prologue	What is MSX	3
STEP 1	Give Your Computer an Order!	6
STEP 2	Let's Write a Program!	17
STEP 3	Are Functions Difficult?	43
STEP 4	Let's Paint a Picture with the MSX	49
STEP 5	MSX Music Class	87
Sample Pr	ograms	97
Design Sh	eets	101
INDEX		104

Preface

This book is written as an introduction for the beginner who will be writing BASIC programs on an MSX computer. It presents easy to understand explanations of the basic principles of MSX-BASIC programming. If you write and then run the programs in the order they are presented in, when you have finished reading this book you should be able to write simple programs by yourself, as well as modify other programs. Let's get used to BASIC by actually using the MSX computer to draw lines, produce sounds and perform other operations.


How this book is organized: _

- 1. This book is written with the assumption that you know how to operate the computer and use the keyboard.
- 2. The subject matter will be much easier to understand if you enter and run each program as you read through the book.
- The command words used in each explanation are framed in large type, so it's easy to look them up in the index.
- Items containing a black mark in the middle of the explanation, provide additional information to make the subject matter easier to understand.

Note:

- If you have carefully followed the contents of this book and there are still unclear points, omissions or other mistakes in the text, please contact your sales representative for additional information.
- Please understand that Japan Victor Corporation can not provide compensation or be responsible for any errors or problems which are the result of the items mentioned above.

Prologue What is MSX



Let's speak with BASIC

It's necessary for us to use words in order to speak. In the same way, in order for people to be able to communicate with a computer, it's necessary to use a programming language such as BASIC.

Up to now, depending on either the computer or the computer manufacturer, both the BASIC and its functions have been different. As a result, when certain types of software, such as programs written in BASIC, are used on a specific computer, that software can't be used on a different kind of computer. However, on computers, both the hardware and the software have been standardized. As a result, all software with the logo will run on any computer.

This means that you can share your software with any of your friends who also have an MSX computer.





The Key is in the Program

In order to make a computer run, you have to study how to write a program.




If a program is entered into the computer, it reads one line of the program at a time, and then operates according to the indicated instructions. In other words, a program is the written set of instructions which contain the appropriate commands for the computer to perform.

Well everybody, do your best to learn how to write your own programs all by yourself.

- 10 REM ********
- 20 REM♥ HC-7GB
- 30 REM *******
- 40 COLOR 15,4:CLS
- 50 LOCATE 5,2
- 60 PRINT "MSX Personal Computer"
- 70 LOCATE 12,5
- 8Ø PRINT "JVC"
- 90 LOCATE 11,7
- 100 PRINT "HC-7GB"
- 110 PLAY "CDEFE"
- 12Ø END



STEP 1 Give Your Computer an Order!



A program uses commands to indicate to the computer what it must do. However, there is also a way to use a computer without using a program. A computer can be run by either method. It isn't necessary to distinguish between the two as they both use the same command language.

Direct Mode

This mode is used to obtain direct results without storing the commands in the computer.


For example,

PRINT "ABC" RETURN

T


The RETURN key is used to inform the computer when the input is finished. Be sure to press the RETURN key at the end of every input line.

ABC OK



The Direct Mode
The computer can read and write characters directly.

Work is performed according to the programmed order.



Program Mode

All input lines start with a line number in the program mode. In this mode, the program is executed after the program is recorded by the computer.

Line Number

The line numbers are used to inform the computer of the correct order of the operations to be performed. Any number from θ to 65529 may be used.

REM

The contents of the remarks statement are ignored when the program runs. They are only used to make the program easier to understand. An apostrophe (') may be used if the REM statement is omitted.

END

When the END statement is encountered, it stops the program.

Next, let's enter this program.

Before starting to write the program the following command should be entered.

NEW RETURN

NEW

This command clears the entire program storage area.

If this command is not used at the beginning of a program, the program commands from the previous program may not be erased. When this happens, it's possible that program commands of the new program may be mixed with the statements already in memory.



If the old programs remain, bugs will appear.

Therefore

10 REM PROGRAM 1 RETURN

Don't forget to press the **RETURN** key when you finish a line.

From now on, enter all programs in this manner.

• It's convenient to memorize this command.

AUTO

This command generates the line numbers automatically on the screen.

Format

AUTO beginning line number, increment

When the first line number parameter is omitted, a value of \emptyset is entered. If the increment parameter is omitted a value of $1\emptyset$ is entered.

AUTO 100,10	line numbers are written from line
	100 in increments of 10
AUTO 20	line numbers are written from line
	20 in increments of 10
AUTO ,10	line numbers are written from line
	Ø in increments of 10
AUTO	line numbers are written from line
	10 in increments of 10

In order to stop automatic line number generation, press the **STOP** key while holding the **CTRL** key down.

• This is a convenient command to use when lines are added to other lines, because an increment of 10 is often used in programs.



You don't have to take the trouble to enter a new program.

This command defines the operations of the functions keys.

Format

KEY function key number, character format

The function keys are numbered from 1 to 10. A character string of up to 15 characters can be defined for any one key, but only five characters can be displayed on the screen.

KEY 6, "PRINT" RETURN

Function key [F6] is defined as PRINT.

Check to see if there were any mistakes when the program was entered. If it's correct, let's try and run the program.

RUN RETURN

This command is used to execute a program in memory.

```
10 REM PROGRAM 1
20 A = 10: B = 5
30 PRINT A,B
40 PRINT A*B
50 PRINT A + B
60 PRINT A - B
70 PRINT A / B
80 END
```


10		
10	5	
10 50		
15		
5		
2		

How did it go? Did everything run properly?

Common Errors

Syntax error in line number

Did an error message like this appear? An error occurs when a command is used that does not appear in BASIC. Generally, typing mistakes are the most frequent reason for error messages. The last number in the error message indicates the line number where the error occurred. Find and correct the mistake in the indicated line number. Please refer to the reference book for more detailed information as there are many other possible error messages besides "Syntax Error". Let's take another look at the program by entering



An error message tells the line number of a mistake.

LIST RETURN

LIST

The LIST command displays the program on the screen.

Format

LIST	The entire program is dis- played on the screen
LIST 20	Only line 20 is displayed on the screen
	All the lines from line 20 to the end of the program are displayed on the screen
LIST - 50	All lines up to line 50 are displayed on the screen
LIST 3Ø – 6Ø	

- · How to correct a program.
- (1) Rewriting a command

Suppose that you want to change the A+B in line 50 to A*B. Move the cursor key to the position of the "+" sign and enter the "*" symbol. Then press the **RETURN** key. The following characters will then appear.

50 PRINT A*B RETURN

(2) Erasing an entire command line To erase line number 70 enter

7Ø RETURN


When a line number is entered and the **RETURN** key is pressed, the computer erases that line number.

```
10 REM PROGRAM #1
20 A = 10 : B = 5
30 PRINT A;B
40 PRINT A * B
50 PRINT A + B
60 PRINT A - B
70 PRINT A/B
80 END
```

After correcting the program, list it again.

```
40 PRINT A*B
50 PRINT A*B
60 PRINT A-B
80 END
```

The corrections which were entered are now part of the program.



There are two ways to erase commands.

· Here is another command which is convenient to memorize.

RENUM

This command is used to correct line numbers

Format

RENUM new line number, old line number, increment

If the new line number is omitted, a value of 10 is entered. If the old line number is omitted the first line number at the beginning of the program is entered. When the increment parameter is omitted a value of 10 is used.

RENUM	1,10,1	Line number 10 is changed to 1. The
		line numbers after that increase by 1.
RENUM	100	The first line number is changed to
		100, and the following line numbers in-
		crease by 10.
RENUM	100,30	Line number 30 is changed to 100. The
		line numbers after that increase by 10.
RENUM	,50	Line number 50 is changed to 10. The
		lines after that increase by 10.
RENUM	,50,5	Line number 50 is changed to 10. The
		lines after that increase by 5.

DELETE

This command erases many lines at once.

Format


DELETE first line number to be erased—last line number to be erased

If the first line number to be erased is omitted, a value of \emptyset is entered.

DELETE 10-40... Lines 10 to 40 are erased.

DELETE -100.... The lines from the beginning of the program to line 100 are erased.

STEP 2 Let's Write a Program!



Let's study some of the basic commands necessary to write a program. Since programs are written in the following order BASIC COMMANDS, FORMAT, PROGRAM LINES AND EXPLANATIONS, when you are entering the program lines by yourself, let's also master BASIC at the same time. Be very careful about entering the comma "," semicolon ";" and other symbols. Just one mistake can make a big difference in the way the program runs.


PRINT

This command is used the most for writing letters and numbers.

PRINT "character string" → The characters enclosed in double quotation marks are displayed on the screen.

PRINT numerical value → The numerical value is displayed on the screen as shown.


PRINT → One line of blanks is displayed on the screen.



Character strings and answers to calculations can also be written instantly.

```
10 PRINT "ABCDEF"
20 PRINT "♥♥♥ "
30 PRINT "5*9"
40 PRINT
50 PRINT 59
60 PRINT 5*9
70 END
```

√ RUN



When the PRINT calculation format is used, the MSX computer can be used just like an electric calculator.

addition PRINT 7+8
subtraction PRINT 15-7
multiplication PRINT 5*8
division PRINT 20/2

Let's enter the next program.

```
10 ? 7 + 8

20 ? 15 - 7

30 ? 5 * 8

40 ? 20/2

50 ? 2000000 * 100000 * 1000000

60 END
```

√ RUN

```
15
8
4Ø
1Ø
2E+14
OK
```

Abbreviated Format


Instead of writing PRINT in each statement, the PRINT command may be omitted and a question mark "?" can be used as an abbreviation.

The answer for line 50 was 2E + 14. This might seem like a strange number, but this just means that the number 2 is followed by a string of 14 zeros.

Mistakes using the comma "," and the colon ";"
 Enter the following program.

```
10 PRINT "ABC"
20 PRINT "A", "B", "C"
30 PRINT 1, 2, 3
40 PRINT "A"; "B"; "C"
50 PRINT 1; 2; 3
60 END
```

RUN



When the comma is used, the first 14 places of the variable number are displayed. Then the first 14 places of the second variable are displayed. When the semicolon is displayed, this indicates that the next filed to be printed will be start at the first character following the preceding field.

The first character in a numeric field is blank so that the minus sign can be printed if necessary. There is also another space at the end of a numeric field, so it will not be connected to the next field when displayed.

This command is used to clear the screen.

CLS

The clear screen command erases the contents of the screen and positions the cursor at the home position (upper left of the screen).


LOCATE

This command moves the cursor to the specified position.

LOCATE horizontal position, vertical position

The small dark square on the screen is known as the cursor. When the PRINT command is used the characters can be written in the cursor position. Because the cursor can be moved freely to any location specified by the program, characters can also be written in any desired location.

10 CLS
20 PRINT "MSX BASIC"
30 LOCATE 10,10 : PRINT "HELLO"
40 END



• Up to now only one command could be written on a line but in BASIC by using the colon ":" any number of commands in a single line. When a number of commands are written in a single line using the colon, this is called a multistatement. If line 30 is written as

```
30 LOCATE 10,10: PRINT "HELLO"
```

this is the same as


30 LOCATE 10,10 35 PRINT "HELLO"

If a program is written in multistatements the program will become shorter. The advantage of this is that the program will run faster. However, if many statements are written in the same line, the program will become harder to understand or correct, so you should avoid using this when possible.

When the power is turned on 24 lines of 37 characters can be displayed on the screen (Screen Mode \emptyset).

The horizontal positions are $\emptyset - 36$ (37 places). The vertical places are $\emptyset - 23$ (24 places).

Any position within this range can be specified. This is how one page of a screen looks in the screen mode.



Command to jump to the specified line.

Format

GOTO line number

This command causes the program to jump to the specified line number. A program is executed in the correct order specified by the program line numbers. The GOTO command is used when you want to change the order of execution.

10 A = 1 20 PRINT A 30 A = A + 1 40 GOTO 20 50 END

√ RUN

```
1
2
3
4
5
6
7
8
```

Do not use this command until you learn how to interrupt execution of a program.

10 A = 1 20 PRINT A 30 A = A + 1

The character "A" used here is called a variable number.

Variable:

A variable is used as a container or storage area for a numerical value which can change. Please remember the name which is attached to the container or storage area.

Format 1

Variable name = expression

In this case the equals sign doesn't mean "equals" or "is the same as". Instead, this means that the value on the right is entered into the value on the left.

10 A = 1

In this case, 1 is entered to the container or storage area called "A"

Format (2)

PRINT variable name

20 PRINT A

In this case the value entered in the storage area called "A" is displayed on the screen.

30 A = A + 1

This statement means that 1 is added to the value of A. This is entered into the storage area A and becomes the new value of A.

The first character of a variable must be an alphabetic character. After that either letters or numbers up to 255 can be used. Variable names of more than three characters can't be distinguished by the computer.


A123—A124 These are all interpreted as the same variable A125—

Only the first two characters can be distinguished by the computer.

40 GOTO 20

This means jump to line 20. When this program is run, numbers will be displayed one after another on the screen without stopping.

The computer will execute the lines up to line 40 one by one. The program never reaches the line 50 END statement because when it gets to line 40 it jumps back to line 20.



To stop execution, read the explanation of STOP on the next page.

STOP

This command is used to interrupt the program execution.


To stop the program, press the \fbox{STOP} key while holding the \fbox{CTRL} key down.

The message


Break in line number

will be displayed on the screen to indicate the point in the program where the interrupt occured.

At this time program execution can be continued by using the CONT command.



The interrupted line number will be stored and used later.



$FOR \ \sim \ NEXT$

Command to repeat the same process

Format

This command is used to repeat the same process within a program a fixed number of times, and then stop automatically.

```
10 FOR I = 1 TO 10
20 PRINT I
30 NEXT I
40 END
```

RUN

1	FOR TO	
2	12 /43	
3		
4		
5		
6		
7	G 53	
8	NIEVT 0	
9	NEXT	
10		
OK	It hasn't reached the final value yet, has it	
•		

The same variable name must be used in the FOR and the NEXT statement.


When the value of a variable is changed in constant steps, the size of each step can be specified with the STEP command.

STEP variable increment

is written like this

```
10 FOR I=1 TO 10 STEP 2
20 PRINT I
30 NEXT I
40 END
```

√ RUN



This program will display the numbers from 1 to 10 on the screen. When the STEP 2 is entered, the numbers displayed on the screen will increase by 2 each time.



If there are many steps in a subroutine, the number of written repetitions can be reduced.

Format

INPUT variable

Up to now, the following method has been used to inform the computer of a variable value.

10 A = 10 20 B = 20 :

At the beginning of the program where the variable values are defined. This is used when you want to change the values of the variables. The program has to be corrected.

The INPUT command is used to input variable values from the keyboard.

10 INPUT A
20 PRINT A * 3
30 END



?

The question mark will appear. This means that the computer is asking you what the value for the variable A in the line 10 should be. For example, if you enter

? 5 RETURN

The computer will perform the calculation on line $2\emptyset$ as 5*3. The answer will be 15.

Using the INPUT command

?

is output, but you have no way of knowing whether character or numeric information is requested, or how you should answer. If characters enclosed in quotation marks (") follow the INPUT command, those characters will be displayed before the question mark.

Format

INPUT "character string"; variable

Well? let's change line 10 in the last program and then try and run the program

1Ø INPUT "HOW MUCH IS A";A 2Ø PRINT A*3 3Ø END

RUN

HOW MUCH IS A? ■

IF ~ THEN

Format (1)

IF condition THEN statement

If a specified condition is met, the operations following the THEN statement are performed. If the condition is not met, the next line in the program is executed.

Format (2)

IF condition THEN line number

If a condition is met, the program will jump to the specified line number. If the condition is not met the next line in the program is executed.

The IF ~ THEN command is used when conditional judgements have to be performed.

10 INPUT A
20 IF A>50 THEN PRINT "GREATER THAN 50"
:GOTO 10
30 PRINT "LESS THAN 50"
40 GOTO 10
50 END

When this program is run, and the question mark appears, enter any number and press the **RETURN** key.


When the number which is input is greater than 50,

GREATER THAN 50

appears. When the number which is input is less than 50, the following message is displayed.

LESS THAN 50

Conditional format				
Symbol	Expression	Meaning		
=:	A = B	A and B are equal		
>	A > B	A is greater than B		
<	A < B	A is smaller than B		
either <> or ><	A <> B	A and B are not equal		
either > = or = <	A > = B	A is greater than B		
either <= or = <	A < = B	A is less than B		



Format (1)

IF condition THEN command (1) ELSE command (2)

If a condition is met the first command is performed. If the condition is not met the second command is performed.

Format (2)

IF condition THEN line number(1) ELSE line number(2)

If the condition is met the first line is jumped to. If the condition is not met, the program control jumps to the second line.

In this command either line numbers or commands may be used in the same line without any problem. For example IF condition THEN command ELSE line number . This command is now used in th preceding program.

10 INPUT A

20 IF A > 50 THEN PRINT "GREATER THAN 50" ELSE PRINT "LESS THAN 50"

30 GOTO 10


40 END



GOSUB~RETURN

This command is used to jump to a subroutine.


Format (1)



After jumping to the specified line number and performing the subroutine, by using the RETURN statement in the subroutine, the program returns to the line following the GOSUB statement.

Format (2)


then returns.



This is similar to the previous example. The program branches to the line number and performs the subroutine, but the program returns to the line number specified in the **RETURN** statement.

• A subroutine is a part of a program which repeats the same operations any number of times when the program is executed. This is extremely convenient as it can be called whenever it is needed.

This small operation contained within a program is called a subroutine.



The next program calculates the surface area of a block.

10 INPUT "HEIGHT";A
20 INPUT "WIDTH";B
30 INPUT "DEPTH";C
40 GOSUB 70
50 PRINT "SURFACE AREA";S
60 END
70 S = 2*(A*B+A*C+B*C)
80 RETURN

When the program is run, and the computer will ask for the values for HEIGHT? WIDTH? and DEPTH?, enter 4, 5 and 6. After line 70 a subroutine is performed. The program returns to line 50 after the **RETURN** in line 80, and then displays the calculation.

SURFACE AREA 148

No matter how large the rectangle is, the calculation for the surface area is the same. Let one subroutine do this calculation.



Format

READ variable 1, variable 2, variable 3...

Data is entered as represented by variable (1), variable (2) and variable (3).

DATA constant(1), constant(2), constant(3)

More than one constant can be contained in a DATA statement.

When the variable value is entered, a number of fixed constants can be entered.

When the variable value is entered, the INPUT statement is used to represent values such as A=10, B=20 etc.

However, there is also another way to enter data besides this method. This is done by using the READ ~ DATA statements.

10 READ X,Y,Z 20 PRINT X;Y;Z 30 DATA 10,20,30 40 END



10 20 30 OK In line 20 the READ X, Y, Z statement reads and enters (loads) the values of X, Y and Z. The values entered for X, Y and Z correspond to the values in either lines 10, 20, or 30.

The READ statement variables can have either a numeric value or a character variable.

For example in the next program, the average test scores for Tom, Dick and Harry can be calculated.

10 FOR I = 1 TO 3
20 READ A\$, B, C, D
30 X = INT((B+C+D)/3)
40 PRINT A\$; "AVERAGE SCORE";X
50 NEXT
60 END
70 DATA Tom, 74, 69, 78
80 DATA Dick, 66, 55, 61
90 DATA Harry, 87, 76, 73

RUN

Tom AVERAGE SCORE 73 Dick AVERAGE SCORE 60 Harry AVERAGE SCORE 78 OK

.

10 FOR I = 1 TO 3 50 NEXT I

The FOR-NEXT commands in lines 10 and 50 will be repeated three times. Three repetitions are necessary to perform the calculations for each of the three students.

Line 20 reads each student's name and grades for English, mathematics and science. This information is contained in the DATA statements in lines 70, 80 and 90.

 $3\emptyset X = INT((B+C+D)/3)$

This statement adds the three grades and then divides them by 3 to get the average.

The INT command is used to obtain the positive integral value (i.e. without any fractions) after the sum of B+C+D is divided by 3. We'll study the INT command in more detail later.

40 PRINT A\$; "AVERAGE";X

The name which was loaded in line 20 and the average calculated in line 30 are displayed.



The calculations are performed in the same manner, but the READ-DATA statement, makes it easy to enter a number of variables.

RESTORE

This command is used to read and enter data after it has already been read in one time.

Data which was loaded by the READ ~ DATA commands normally can't be read again after it has been loaded once. However, it is often necessary to use the same data a number of times. The RESTORE command enables the data to be loaded again after it has already been loaded once.

Format 1

RESTORE

10 READ A, B, C 20 RESTORE 30 READ D, E, F 40 PRINT A;B;C 50 PRINT D;E;F 60 END 70 DATA 10, 20, 30

√ RUN

10 20 30 10 20 30 OK

Format 2

RESTORE line number


When this command is used the data in the specified line number will be loaded next.

10 READ A, B, C
20 RESTORE 90
30 READ D,E,F
40 PRINT A;B;C
50 PRINT D;E;F
60 END
70 DATA 10, 20, 30
80 DATA 40, 50, 60
90 DATA 70, 80, 90

RUN

10 20 30 70 80 90 OK

STEP 3 Are Functions Difficult?



The way functions work is rather simple. An answer is given for a value based on a preset processing operation. MSX computers have many functions, each of which performs a preset process.

Lets study how to use some of the more useful functions.



Preset processing of variables is efficient.

CHR\$ function

Format

This returns the character which corresponds to the numeric or variable value.

CHR\$ (numeric value)	
CHR\$ (variable value)	
The variable value must be between \emptyset to 255.	
PRINT CHR\$(65) RETURN	
$\hat{\Box}$	
Α	
OK ■	

The character "A" is displayed on the screen. This is because the 65th character in the character code chart is "A".

The computer can also display other characters besides the ones on the keyboard. The chart of the assigned numbers for characters and graphics is contained within the computer. This number which is assigned to a character is called the character code or ASCII code.

Character Code Chart

	0	1	2	3	4	5	6	7	8	9	A	В	C	D	E	F
0		+		0	@	P		p	Ç	É	á	Ã	_	1	α	=
1	0	1.	!	1	A	Q	a	q	ü	æ	í	ã	٠,	X	ß	±
2	•	T	Ш	2	В	R	b	r	é	Æ	ó	Ĩ		H	Γ	2
3	•	+	#	3	C	S	С	s	â	ô	ú	ĩ		•	П	≤
4	•	+	\$	4	D	T	d	t	ä	ö	ñ	Õ	-		Σ	ſ
5	+	+	%	5	Е	U	e	u	à	6	Ñ	ð			σ	J
6	•	1	&	6	F	V	f	v	å	û	a	Ũ			μ	÷
7		-		7	G	W	g	w	ç	ù	Ō	ũ		×	γ	~
8	٠	-	(8	Н	X	h	x	ê	ÿ	ċ	IJ		Δ	Φ	0
9	0)	9	I	Y	i	У	ë	Ö	F	ij		‡	θ	•
A	0	-	*	:	J	Z	j	z	è	Ü	7	3/4		ω	Ω	-
В	8		+	:	K]	k	1	ï	¢	1/2	-	1/1		S	7
C	9	×		<	L	1	1	1	î	£	1/4	0	11		∞	n
D	7	1	_	=	M]	m	1	ì	¥	i	%	▼		φ	2
E	Ħ	1		>	N	^	n	-	Ä	Pt	<	ग	^		ϵ	
F	₩	+	1	?	0	_	0	Δ	Å	f	>	§	•		η	

The character code in the chart above is determined as follows. (horizontal column number) × 16 + (vertical column number) = (assigned character code)

INT

This returns the integer and removes any fractions. This command is used for positive numbers.

Format

INT (numeric value)

PRINT INT (3.14) RETURN

The fraction of 3.14 is removed and the positive number 3 is displayed.

RND

This command returns a random number between 1 and \emptyset .

Format

RND (numeric value = -1, \emptyset or 1)

```
10 FOR I = 1 TO 5
20 X = INT(RND(1) * 10)
30 Y = INT(RND(1) * 10)
40 PRINT "X = ";X;"Y = ";Y
50 NEXT I
60 END
```

When this program is run X is equal to a value ranging from \emptyset to 9. Y is equal to a value from 1 to $1\emptyset$. This operation will write out the results five times.



Any number of random probability can be output just like throwing dice.

INKEY\$

This command is used to represent characters input from the keyboard.

Format

INKEY\$

If a key on the keyboard is pressed, the value of that character is returned. If no key on the keyboard is pressed, a space (null string) is returned for that value.

10 A\$ = INKEY\$
20 IF A\$ = " " THEN GOTO 10
30 PRINT A\$
40 END

When this program is run, press any key on the keyboard. The character which was entered will be displayed and the program will end.


```
10 X = 10:Y = 10:CLS
20 A$ = INKEY$
30 IF A$ = "S" THEN X = X - 1:GOTO 70
40 IF A$ = "D" THEN X = X + 1:GOTO 70
50 IF A$ = "E" THEN Y = Y - 1:GOTO 90
60 IF A$ = "X" THEN Y = Y + 1:GOTO 90
70 IF X < 0 THEN X = 0
80 IF X > 28 THEN X = 28
90 IF Y < 0 THEN Y = 0
100 IF Y > 20 THEN Y = 20
110 LOCATE X,Y:PRINT "♥"
120 GOTO 20
130 END
```

This program displays the "♥" on the screen. If "S" is entered it will move to the left side. If "D" is entered it will move to the right side. If "E" is entered it will move up. If "X" is entered it will move down.

Program flow can be controlled from the key-



STEP 4 Let's Paint a Picture with the MSX!



Let's draw pictures with the MSX!

Lets's study some commands and draw some pictures now. We'll combine some of the commands that have appeared before to create some graphics.

SCREEN

This command selects the screen.

Format

SCREEN mode

The screen mode is specified by values from \emptyset to 3.

MSX computer has four kinds of screen modes in all.

Mode Ø: Text Screen 1

37 characters × 24 lines (Default setting)

Mode 1: Text Screen 2

29 characters × 24 lines (Default setting)

Mode 2: High Resolution Graphic Mode

256 dots × 192 dots

Mode 3: Low Resolution Graphic Mode

(Multi-color Mode)

256 dots × 192 dots (64 × 48 blocks)

Up to now we have only used Screen Mode Ø.


The screen is automatically set to Mode \emptyset when the power is turned on

The Text Mode and Graph Mode are used as follows.

To display characters Text Mode
To display drawings Graphic Mode

Use Text Screen 1 or Text Screen 2 to display any character on the screen

Mode 2 or Mode 3 must be used to display any graphics.



You have just been using Text screen 1 of mode \emptyset . There are three other kinds of screen modes.

COLOR

This command is used to select colors for the screen.

In MSX BASIC there are 16 colors which may be used. But they are decided by the color command.

Format

COLOR character color code, background color code, border color code

This command determines the color of characters and lines, the background and border of the screen.

When the computer is turned on it is preset to

COLOR 15, 4, 4

White characters (color code 15)
Dark blue background (color code 4)
Blue border (color code 4) — Valid only in Mode 1.

The border area is not displayed because the screen in Mode \emptyset . Change the color of the screen by refering to the Color Code Chart and making the appropriate modifications.

 Color Code Chart 					
0: clear	4: dark blue	8: red	12: dark yellow		
1: black	5: light blue	9: light red	13: purple		
2: green	6: dark red	10: yellow	14: gray		
3: light green	7: blue	11: light yellow	15: white		

• Abbreviated Format To change just the character color


COLOR 1

To change just the background color

COLOR,2

To change the outline color

COLOR,,3



I made a mistake. The characters and background were the same color.


Well, let's try and paint a picture with the MSX computer and the next program.

This program used circles and straight lines to make a snowman and a house. Now let's make the snow fall in the sky.

10 REM SNOWMAN	Program title set mode		
20 SCREEN 2	set mode		
30 LINE (0,140) - (255,140), 5	back and also		
40 PAINT (70,40), 5	background sky		
50 LINE (25,110) – (50,90), 6			
60 LINE (50,90) – (80,110), 6	roof of the house		
70 LINE (80,110) – (25,110), 6			
80 PAINT (50,100), 6	J		
90 LINE (30,140) – (70,110), 10, BF	house		
100 LINE (35,140) – (45,115), 1, BF	door		
110 LINE (53,125) – (60,115), 3, BF	window		
120 CIRCLE (150,120), 40,15			
13Ø CIRCLE (15Ø,6Ø), 25,15			
140 PAINT (150,120), 15	snowman		
150 PAINT (150,60), 15			
16Ø PAINT (15Ø,83), 15)		
17Ø CIRCLE (14Ø,6Ø), 5,1			
18Ø CIRCLE (16Ø,6Ø), 5,1	eyeballs		
190 PAINT (140,60), 1	- Maria		
200 PAINT (160,60), 1	J		
210 LINE (135,70) – (150,75), 1	mouth		
22Ø LINE(15Ø,75) – (165,7Ø), 1			
23Ø CIRCLE (15Ø,1ØØ), 6,9			
240 CIRCLE (150,115), 6,9	buttons		
250 PAINT (150,100), 9	5.040 P.S. W. S. 1020		
260 PAINT (150,115), 9)		
27Ø LINE (145,35) – (16Ø,15), 13			
28Ø LINE (16Ø,15) – (175,22), 13			
290 LINE (175,22) – (170,45), 13	bucket on head		
300 LINE (170,45) - (145,35), 13 310 PAINT (160,30), 13			

320 FOR I = 1 TO 500
330 X = INT(RND(1) * 256)
340 Y = INT(RND(1) * 91)
350 PSET (X, Y), 15
360 NEXT I
370 GOTO 370
380 END

To paint a line with the MSX computer, the position of the dots on the screen must be displayed one by one. In order to paint the picture of a snowman, the positions of the necessary points are drawn in a diagram.




Did you draw it correctly? If you make a mistake in the numbers, the snowman might not have a head, or the inner colors might spread all over the screen.

SCREEN

20 SCREEN 2

This selects a high resolution mode of 256 (horizontal) \times 192 (vertical) dots. As a result there are 256 individual horizontal points and 192 vertical points which can be painted. These are known as graphic coordinates.



If you're thinking that it's 256 and not 255, make sure that you're counting the zero.

LINE

Command for drawing a straight line

3Ø LINE(0,14Ø) - (255,14Ø), 5

This command draws a line from point A $(\emptyset,14\emptyset)$ to point B(255,100) in color number 5 (light blue).

Format

LINE (starting point) - (ending point), color code

When the color code is omitted, the color specified for the character code is used.

When a line is drawn by the LINE statement, it can also be abbreviated as follows.

```
50 LINE (25,110) - (50,90), 6
60 LINE (50, 90) - (80, 110), 6
70 LINE (80, 110) - (25, 110), 6
```




```
50 LINE (25, 110) - (50,90), 6
60 LINE - (80,110), 6
70 LINE - (25,110), 6
```

Command for painting a rectangle

```
90 LINE (30,140) - (70,110), 10, BF
```

In this command a diagonal line is drawn from point A (30,140) to point B (70,110) and connected. This forms the diagonal of a rectangle which will be painted yellow (color mode 10). The inside of this rectangle will be painted yellow.



You can draw a rectangle by just specifying 2 points.

Format

LINE (starting point) - (ending point), color code, B

Either B or BF can be used to specify the painting of the inside of the rectangle.

PAINT

Command to paint colors

40 PAINT (70,40), 5

This command will paint the area from the point (70,40) in light blue (color code 5).

Be careful when you use this command, because if the area to be painted isn't surrounded by lines, the entire screen will be filled in with the specified color.



The color will flow out if the outline isn't completely connected.


Format

PAINT (starting point), color, color of high resolution

The high color resolution can't be used on SCREEN 2. The color code designations for painting SCREEN 2 graphics are not the same. The colors for SCREEN 3 graphics must be specified separately.

```
10 SCREEN 2
20 LINE(100,10) - (50,100), 1
30 LINE - (200,150), 1
40 LINE - (100,10), 1
50 PAINT(100,80), 1
60 GOTO 60
70 END
```

This program paints a black triangle when it is run. After the triangle is drawn, it then paints the inside portion black.



```
10 SCREEN 3
20 LINE(100,10) - (50,100), 1
30 LINE - (200,150), 1
40 LINE - (100,10), 1
50 PAINT(100,80),2,1
60 GOTO 60
70 END
```

When this program is run it paints a black triangle. After the triangle has been drawn, it paints the inside portion green.

CIRCLE

Command for drawing an ellipse

120 CIRCLE(150,120), 40,15

This command draws an ellipse with a center located at position (150,120). The radius is 40 dots (pixels), and the ellipse will be painted white (color code 15).

Format

CIRCLE (center point), radius length (in dots), color code

```
10 SCREEN 2
20 FOR A = 10 TO 60 STEP 10
30 CIRCLE(128,96), A, 1
40 NEXT A
50 GOTO 50
60 END
```

When this program is run, it draws six black ellipses with different radii each having the same center.

In line 50 the statement GOTO 50 causes the ellipses which were drawn to be displayed continuously. To stop the display press the **STOP** and **CTRL** keys.



A circle is defined by the location of the center and the length of the radius. If you don't specify the color, it will be the same as the text characters.

The correct format for the circle command is shown below.


CIRCLE (center point), radius length (in dots), color code, starting point degree, ending point degree, ratio (of radius length to width).

The parameters from the color code to the ratio may be omitted.

- When the color code parameter is omitted, the color specified in the COLOR command is used.
- When the start point degree parameter is omitted a value of Ø is used.
- When the end point degree parameter is omitted a value of 6.28 is used.
- A value of 1 is used when the ratio parameter is omitted.
- Set the ratio to 1.3 to draw a circle.

The start point angle is defined as the first position where the circle will be drawn from.

The end point angle is defined as the last position where the circle will be drawn to.




When you only want to draw 90° of a circle the end point is calculated as follows. $3.14 \times (90^{\circ}/180^{\circ}) = 1.57$

The rate is the ratio of the horizontal axis to the vertical axis of a circular geometric figure.

- A value of 1 is a circle.
- A value of less than 1 causes a horizontal elipse to be drawn.
- A value greater than 1 causes a vertical elipse to be drawn.

When the ratio is less than 1, a horizontal elipse is displayed. When the ratio is greater than 1, a vertical elipse is displayed.




Remember that when the ratio is less than 1, the radius specification represents the maximum length of the radius.

```
10 SCREEN 2
20 CIRCLE(60,50), 40,1
30 CIRCLE(80,150), 50,1, -1.57, -3.14,1
40 CIRCLE (160,100), 60,1,,,2
50 GOTO 50
60 END
```

Line 20 draws the circle.

The parameters within the broken line can be omitted.

In line 30 the arc shown below is drawn.



The minus sign connects the center of the circle with the start and end points.

In line 40 a circle is drawn.

The parameters inside the broken lines may be omitted.

```
350 PSET (X,Y), 15
```

This command draws a white dot at the graphic coordinates (X,Y). When no value is specified, X is preset to 320 and Y to 360.

```
320 FOR I = 1 TO 5000


330 X = INT(RND(1) * 256)

340 Y = INT(RND(1) * 91)

350 PSET(X,Y), 15

360 NEXT I
```

These commands draw 5000 white dots at the graphic coordinates (256,900). The first value indicates the horizontal position, and the second value indicates the horizontal position.



Format

PSET (horizontal value, vertical value), color code

```
350 PSET (X,Y), 15
```

This command draws a white dot at the graphic coordinates (X,Y). When no value is specified, X is preset to 320 and Y to 360.

```
320 FOR I = 1 TO 500


330 X = INT(RND(1) * 256)

340 Y = INT(RND(1) * 91)

350 PSET(X,Y), 15

360 NEXT I
```

These commands draw 500 white dots at the graphic coordinates (256,90). The first value indicates the horizontal position, and the second value indicates the horizontal position.



Format

PSET (horizontal value, vertical value), color code

Command to erase a point at a specified position.

Format

PRESET (horizontal value, vertical value), color code.

If a color code other than the specified background is specified, it will be the same as the PSET color code.

This is O.K.

All the commands which were used in the program "Snowman" have been explained.

Enter the characters RUN.




Hey! Why did you make the eyes different colors?

Format

DRAW "character string"

A point moves according to the specified character string and a figure is drawn.

The DRAW command position is directed as specified by the characters U, D, L or R. The specified shape is drawn, within the number of dots specified for the range.




You can move an image in eight different directions.



It's also very easy to draw an zigzag line.

10 COLOR 15,1,1
20 SCREEN 2
30 DRAW "BM50,50"
40 DRAW "F60 G20 H60 E20"
50 GOTO 50
60 END






Line 10 defines the screen color. Line 20 defines the screen mode.

30 DRAW"BM50,50"

This statement specifies the point where the drawing will start.




Even if you know the directions, if you don't know the starting point you can't draw anything.

Format

DRAW "BM X-coordinate, Y-coordinate"

40 DRAW "F60G20H60E20"

A rectangle will be drawn starting at the point (50,50). The sides of the rectangle will be then be drawn 60 dots to the lower right. 20 dots to the lower left, 60 dots to the upper right and 20 dots to the upper right.



It's easy to change the length of a rectangle, but it's somewhat harder to change the angle.

Next lets draw a number of rectangles in a row.

```
10 COLOR 15,1,1
20 SCREEN 2
30 DRAW"BM50,50"
40 FOR I = 1 TO 20
50 DRAW"BM + 5,0"
60 DRAW"F60G20H60E20"
70 NEXT I
80 GOTO 80
90 END
```

The statements in line 40 FOR I=1 TO 20 and line 70 NEXT I cause 20 rectangles to be drawn. However, they will all be drawn in the same position. In order to see each separate rectangle, each rectangle should be moved over a little bit from the position of the previous rectangle. This is done by the command in line 50.

```
5Ø DRAW"BM + 5,0"
```

This statement moves the starting point of each rectangle that is drawn, 5 dots to the right each time.

Format

```
DRAW "BM , ""

"Vertical motion | + moves down | (Y coordinate) | - moves up


Horizontal motion | + moves to the right | (X coordinate) | - moves to the left
```

For example, the statement

```
50 DRAW"BM+5,+2"
```

causes 20 rectangles which shift to the lower right side of the screen to be drawn.

In the DRAW command, instead of using parameters enclosed in quotes like F60G20H60E20, character variables can also be used.



10 COLOR 15, 1,1

20 SCREEN 2

30 DRAW"BM50,50"

40 FOR I = 1 TO 20

50 DRAW"BM + 5,0"

60 A\$ = "F60G20H60E20"


70 DRAW"XA\$;"

80 NEXT I

90 GOTO 90

100 END

When this program is run it produces the same results as the program on page 70.



The rectangles are layered like a row of dominoes.

Moving the Sprite figure

Up to now we have been studying how to draw shapes using the LINE and CIRCLE commands, although using these commands to move figures is somewhat difficult.

The SPRITE command is extremely useful for this purpose. Before studying the SPRITE command, lets learn a little bit more about the background, Sprite and boundary screens. In this case, the boundary screen is not used for screen display and will be omitted.

★ Background Screen

The background screen is used for graphics which do not move. Up to now, all of the LINE and CIRCLE commands have not been moved on the background screen. There are four modes for the background screen. The SCREEN command is used to change these modes.

* Sprite Screen


The Sprite screen is used for the purpose of moving graphic figures. There are Ø to 31 Sprite screen numbers which can be attached to the Sprite screen. This means that there are 32 Sprite screens in all. The screen numbers are displayed in ascending order. Only one desired figure can be loaded at a time, from one screen to the next. However, if the Sprite screen number is changed, the same figure can be displayed on up to 32 screens.



This screen is only one layer, but there are actually 33 layers.

If nothing is written on the Sprite screen, it is transparent; therefore up to 33 layers of images can be viewed on the monitor.

Thus, when a figure drawn on a sprite screen at the back is over lapped by one drawn on a sprite screen nearer the front the overlapped portion of the figure at the back will disappear. This makes it possible to give display an appearance of depth.



Sprite screens are transparent except where they contain figures.


In order to use the Sprite function, the following steps are necessary.

- Either 8×8 dot or 16×16 dot Sprite patterns must be defined.
- The data for characters to be displayed using the Sprite function must be defined in character strings.
- Both the Sprite screen number which the Sprite pattern will be displayed on, as well as the display size (standard or expanded) must be specified.
- · Sprite patterns must be displayed on Sprite screens.

Let's make a Sprite pattern.

First an 8×8 dot figure must be defined.

In binary notation, a blank is expressed as \emptyset and a dark point as a 1.



A Sprite pattern can be written like this, by using a character string composed of eight character codes.

When the figure above is defined as a Sprite pattern, it is expressed by using a character string like this.

If decimal notation is not used, either binary or hexadecimal expressions can be written as shown below.

Binary	
CHR\$(&B11011000) + CHR\$(&B01010000) +	
Hexadecimal	
CHR\$(&HDH) + CHR\$(&H5Ø) +	
CHR\$(&HC7)	

When binary or hexadecimal expressions are used, the following symbols must be used before the numbers.

Binary &B Hexadecimal &H Up to 256 8×8 dot Sprite patterns can be defined on the MSX computer. Each of them is given a special Sprite pattern number.

Let's assign Sprite pattern number \emptyset to the pattern which was just created.

```
SPRITE$(0) = CHR$(216) + CHR$(80) +
CHR$(248) + CHR$(168) +
CHR$(115) + CHR$(62) +
CHR$(126) + CHR$(199)
```

SPRITE\$

Command to define a sprite pattern

Format

SPRITE\$ (pattern number) = figure expressed as a character string

Sprite patterns can only be displayed in SCREEN modes 1 to 3. Sprite pattern sizes are determined as follows.

SCREEN,Ø	8×8	dot	standard
SCREEN,1	8×8	dot	expanded
SCREEN,2	16×16	dot	standard
SCREEN,3			

The PUT SPRITE command is used to display a Sprite pattern on the screen.

PUT SPRITE

Command to display a sprite

Format

PUT SPRITE Sprite screen number, Sprite position, color code, Sprite pattern number

10 COLOR 15,4,7

20 SCREEN 2,0

30 FOR N=1 TO 8

40 READ A : B\$ = B\$ + CHR\$(A)

50 NEXT N


 $6\emptyset \text{ SPRITE}(\emptyset) = B$ \$

70 PUT SPRITE 0,(128,96),15,0

8Ø GOTO 8Ø

90 END

100 DATA 216,80,240,168,115,62,126,199



The rabbit in the program above was displayed in white.

70 PUT SPRITE 0,(128,96),15,0


This command specified Sprite screen number \emptyset , position (128,96), color code 15, and pattern number \emptyset to be drawn.

If a Sprite pattern is not defined by the SPRITE\$ command before executing the PUT SPRITE command, nothing will be displayed on the screen.

If line 20 is changed to

20 SCREEN 2,1

and the program is run the rabbit will be twice as big as before. In this case, the 8×8 Sprite dot pattern is expanded dot by dot to twice its original size.



The character string for the ear is 11011000. Oh don't move! It just became 11000000.

Binary and Hexadecimal Conversions

Binary Number	Decimal Number	Hexadecimal Number
Ø	Ø	Ø
1	1	1
10	2	2
11	3	3
100	4	4
1Ø1	5	5
110	6	6
111	7	7
1000	8	8
1001	9	9
1010	10	A
1Ø11	11	В
1100	12	С
11Ø1	13	D
1110	14	Е
1111	15	F

• To convert a binary to a hexadecimal number

· To convert a hexadecimal number to a decimal number

D $8 = 13 \times 16 + 8 \times 1 = 216$ $\downarrow \downarrow \downarrow$ $16^{1} 16^{0}$ $\parallel \parallel$ 16 1

The rabbit pattern is the same when it is represented by character strings written in binary, decimal or hexadecimal.

• To move a Sprite pattern

```
10 COLOR 15,4,7
20 SCREEN 2,1
30 FOR N = 1 TO 8
40 READ A:B$ = B$ + CHR$(A)
50 NEXT N
60 SPRITE$(0) = B$
70 PUT SPRITE 0,(0,90), 15,0
72 C = INT(RND(1)*15)
74 FOR I = 1 TO 256
76 PUT SPRITE 0,STEP(-1,0), C, 0
78 NEXT I
80 GOTO 72
90 END
100 DATA 216,80,240,168,115,62,126,199
```

The parts which are underlined are rewritten or modified. When this program is executed, the rabbit will change colors and move from right to left. The program can be stopped and started again by pressing the **STOP** key.


```
76 PUT SPRITE Ø,STEP(-1,Ø), C,Ø
```

The rabbit can only be moved from position $(\emptyset,90)$ by using the STEP command to indicate the variation range (-1,0).


Format

STEP (horizontal variation, vertical variation)

Why don't you try changing the parameters in the STEP $(-1,\emptyset)$ command of line 70 and observe the results?



Creating 16×16 Dot Patterns
 The increase in the 16×16 pattern is quite evident. In binary notation blank points are expressed by Ø and dark points by 1.



I'm the binary rabbit. If you make me a decimal rabbit, I'll be light and easier to write.

Character strings in binary notation must be created in the order shown below.

01100001	100000000
11110011	11000000
10110011	01000000
00110011	00100000
ØØ111111	
Ø1111111	
11101101	
11111111	
e.	
*	
•	
A 200	
1.	
858	


10000000	DEERARIE
②③(3)(4)(5)(6)	25)

Character string DATA

97, 243, 179, 51, 63, 127, 237, 255

127, 63, 31, 31, 31, 63, 72, 145 128, 192, 64, 32, Ø, 128, 192, 192

130, 55, 255, 250, 248, 248, 112, 224



I'm those numbers.

Enter the following modifications to the previous program. Except for these changes, it should run the same as it did before.

20 SCREEN 2, 2 30 FOR N = 1 TO 32

100 DATA · · · ·

10 COLOR 15,4,7

20 SCREEN 2,2

30 FOR N = 1 TO 32

40 READ A : B\$ = B\$ + CHR\$(A)

50 NEXT N

60 SPRITE(0) = B\$

70 PUT SPRITE 0,(128,96), 15,0

80 GOTO 80


90 END

100 DATA 97, 243, 179, 51, 63, 127, 237, 255

110 DATA 127, 63, 31, 31, 31, 63, 72, 145

120 DATA 128, 192, 64, 32, 0, 128, 192, 192

130 DATA 130, 55, 255, 250, 248, 248, 112, 224



Next time let's make it like this!

ON SPRITE GOSUB

Format

ON SPRITE GOSUB line number

This command calls the subroutine starting at the specified line when the locating of figures on two sprite screens are the same.

SPRITE ON/OFF/STOP

Interruptions can be generated by using the SPRITE ON command.

Format

SPRITE ON

The subroutine specified by the ON SPRITE GOSUB command will then be executed.

SPRITE OFF

This command is used to prevent interrupts from being generated. After this command has been executed, the ON SPRITE GOSUB command can't be used until a SPRITE ON command is executed.

SPRITE STOP

This command stops Sprite interrupts. The difference between this and the SPRITE OFF command is that when t is stopped, it is evaluated whether or not there was an error in SPRITE. If there is an error when Sprite is stopped, and the SPRITE ON command is executed, an interrupt is immediately generated. In this program, when Sprite screen number \emptyset and 1 are used and the program execution reaches line 14 \emptyset , the buzzer sounds thirty times and the program stops.

```
10 SCREEN 2,1
20 \text{ A} = CHR\$(216) + CHR\$(80) + CHR\$(240) +
        CHR$(168) + CHR$(115) + CHR$(62) +
        CHR$(126) + CHR$(199)
30 \text{ B}$ = CHR$(56) + CHR$(124) + CHR$(56) +
        CHR$(254) + CHR$(56) + CHR$(56) +
        CHR\$(68) + CHR\$(130)
40 \text{ SPRITE}(0) = A$
50 \text{ SPRITE}(1) = B$
60 ON SPRITE GOSUB 130
70 SPRITE ON
 80 FOR I = 0 TO 191
90 PUT SPRITE 0,(0+1,96),1,0
100 PUT SPRITE 1,(255-1,96), 10,1
110 NEXT I
120 END
130 SPRITE OFF
140 FOR J = 1 TO 30: BEEP: NEXT J
150 RETURN 120
```

Drawing character on the graphic screen

Up to now we've learned how to draw both text characters and graphics. However, the screen modes have been separated into text and graphic modes. Text and graphics couldn't be used together.

The next program shows how to write text characters on a graphic screen.



When you want to write text characters in the graphic mode, it must be specified first.

```
10 SCREEN 2
20 LINE(120,110) - (155,95),9
30 LINE - (190,110),9
40 LINE - (120,110), 9
50 PAINT(160,105), 9
60 LINE(135,140) - (175,110), 15,BF
70 LINE(155,125) - (165,115), 5,BF
80 LINE(140,140) - (150,120), 1,BF
90 OPEN"GRP:" FOR OUTPUT AS #1
100 DRAW"BM120,70"
110 PRINT #1,"HOUSE"
120 CLOSE #1
130 GOTO 130
140 END
```

To write alphanumeric characters on a graphic screen execute the following command.

90 OPEN "GRP:" FOR OUTPUT AS #1

When this command is executed, the computer is informed that text characters can be written on the graphic screen.

After this, the PRINT command can be used just like it is in the text screen mode. The characters "HOUSE" are written by executing the command

110 PRINT #1,"HOUSE"

100 DRAW "BM 120,70"

This specifies the beginning of the display position.

STEP 5 MSX Music Class



Let's study some of the commands which make music. These commands are BEEP, PLAY and SOUND. However the SOUND command is somewhat difficult so it won't be covered here.

BEEP

This makes the buzzer sound.

Format

BEEP

Beeps the speaker.

10 FOR I = 1 TO 10

20 BEEP

30 NEXT I

40 END



The buzzer will ring 10 times

The BEEP command can't change the tone or length the tone will sound.





Format

PLAY "character string"

Music expressed by a character string is played when this command is executed.


PLAY "CDEFRGAB" RETURN

This instruction plays "Do Re Mi Fa", pauses briefly and then plays "So La Ti".

The characters A to G each represent a note of the musical scale.

character	C	D	E	F	G	A	В
note	Do	Re	Mi	Fa	So	La	Ti

The character "R" represents a pause in the music. This is known as a rest. A melody can be played by entering PLAY, followed by the characters A to G or R enclosed in quotation marks.



· Specifying Octaves

The MSX computer can play eight octaves. In order to designate an octave use the letter "O" and a number (1 to 8). This must be written before the characters (A to G) which represent the tones of the scale.

PLAY "O3 CDEFGAB O4 CDEFGAB O5 CDEFGAB" RETURN

This plays the scale for three octaves. Once a value for O is specified, the same value is maintained until a new value for O is encountered. When the computer is turned on the preset value for O is (O4).

· Writing Sharps and Flats

In order to be able to play a melody, it is also necessary to be able to play a half tone up (sharp) and a half tone down (flat).

Sharps and Flats are written as follows.

A half tone up...... # or + are written immediately after the characters A to G.

A half tone down............ A minus sign "-" is written immediately after the characters A to G.

The symbols "#", "+", and "-" are the same as the black keys on the piano.

There are also some half tones which are exceptions. C-is B, F-is E, B+ is C and E+ is F

Hey are there really that many black keys?

· Writing the length of a tone

If there is a tone length parameter after the characters representing the notes, those notes are played for the specified period of time. If there is no number following a note, that note is played for the length of time equal to the number following the character L

PLAY "C1D2E4F8R1G16A32B64" RETURN

The notes CDEF are gradually played faster and faster. After a rest the notes GAB are played even quicker. The tone length

PLAY "C4D4E4F4G4A4B4"

It's rather inconvenient to specify the time value of a quarter note for each note. In cases like this, it's easier to write it out as shown below.

can be specified quite precisely by using a value from 1 to 64.

PLAY "L4 CDEFGAB"

Isn't it easier to write it out like that?

If there are numbers following the characters A to G and R, the tones will be played according to the indicated length. The letter "L" is used to specify the tone length. The value specified for L is maintained until a new value for L is encountered. When the computer is turned on the preset tone length value is "L4".

note name	whole note	1/2 note	1/4 note	1/8 note	1/16 note	1/32 note
musical symbol	o		٦	3	A	A
value of L	1	2	4	8	16	32

· Dotted notes

A dotted note is a note followed by a dot. Its length is 1.5 times larger than the specified value for the tone length.

A period after the numeric value for the time length indicates a dotted note.

note name	dotted whole note	dotted 1/2 note	dotted 1/4 note	dotted 1/8 note	dotted 1/16 note	dotted 1/32 note
musical symbol	٥٠	J.	J.	D.	D.	J.
tone length	0+0	J + J	1+1	1.1	D+ A	A.A
specified value	1.	2.	4.	8.	16.	32.



A dotted note is played just like it is written.

• Writing rests

A rest is a pause in the melody. Rests are written the same way notes are. The number following the R specifies the value of the rest.

rest name	whole rest	1/2 rest	1/4 rest	1/8 rest	1/16 rest	1/32 rest	1/64 rest
musical symbol	-	-	1	7	7	¥	ji ji
value of R	1	2	4	8	16	32	64

· Setting the Tempo

The tempo within an entire piece will speed up and slow down at times. This is accomplished by using the T parameter followed by a number from (32 to 255). The larger numbers indicate faster tempos.

A value indicated for the parameter will be maintained until another T value is encountered. When the computer is turned on the preset value for the tempo is T120.

· Setting the volume

The V parameter and the numbers which follow (1 to 15), indicate the volume.

PLAY "L1V3CV6DV9EV12FV15G" RETURN

The volume will gradually increase as the scale is played. When V is specified there is no sound at all.

When the computer is turned on, the preset value for the volume is V8.

· Specifying the tone

To change the tone color, use either the S or M parameter followed by a number.

S changes the envelope shape.

M changes the envelope cycle.

The envelope can be specified by using the S and M parameters. The cycle pattern of the volume is changed when this occurs. At this time the vibrato characteristic is specified by the S parameter, and the vibrato speed is specified by the M parameter.

The S and M parameters should be used as a pair. The S and M parameters can not be used at the same time as the V (volume) parameter.

The following program changes the tone and plays the scale.

10 FOR S = 0 TO 14
20 FOR M = 1000 TO 100000 STEP 2000
30 PLAY "S = S;M = M;CDE"
40 NEXT M
50 NEXT S
60 END

The value of the S parameter can be specified from \emptyset to 15. The value of the M parameter can be specified from 1 to 65535.

PLAY "S10M3000 CDEFGAB" RETURN

Try changing the numeric values which follow the S and M parameters to produce a variety of different tones.



Now let's make the MSX computer perform "Home on the Range".

10 PLAY "T128"
20 PLAY "O4L4CCFGA2L8FED4. B - B - 4"
30 PLAY "B - 2AB - O5C2O4FFF4. EF4G2."
40 PLAY "G2L4CCFGA2L8FED4. B - 8B - 4"
50 PLAY "B - 2B - B - A4. GF4E4. FG4F2."
60 END



The MSX computer isn't all that simple. It can also play two and three note chords.

For example, to play C E G at the same time, place a comma between the notes of the chords as shown below.

PLAY "C","E","G"

Once you can play a scale, your repetoire will increase considerably.



Sample Programs

Sample 1

```
10 REM COLOR GRAPHICS
20 SCREEN 2
30 COLOR 15, 1, 1
40 C=1
50 FOR X=35 TO 215 STEP 30
60 FOR Y=35 TO 155 STEP 30
70 PLAY "V14L64O6A"
80 CIRCLE (X, Y), 30, C
90 PAINT (X, Y), C
100 C=C+1
110 IF C>15 THEN C=1
120 NEXT Y
130 NEXT X
140 GOTO 140
150 END
```

When RUN is entered, this program draws circles in 15 colors across the entire screen. To stop the program, press CTRL + STOP.

Sample 2

```
90 PRINT "NOTE | B | C | D | F | G | A | C | "
100 PRINT "
               110 PRINT "
               120 PRINT "KEY | Z|X|C|V|B|N|M|, | . | / | "
13Ø PRINT "
               140 PRINT "NOTE | B | C | D | E | F | G | A | B | C | D | "
150 PRINT "
               "
160 PRINT "PLAY NOTES BY PRESSING KEYS
   (Z-/, A-;)
17Ø A$ = INKEY$:IF A$ = " " THEN 17Ø
180 IF A$ = "Z" THEN PLAY "O3B"
190 IF A$="X" THEN PLAY "O4C"
200 IF A$ = "C" THEN PLAY "O4D"
210 IF A$ = " V " THEN PLAY "O4E"
220 IF A$ = " B " THEN PLAY "O4F"
230 IF A$ = "N" THEN PLAY "O4G"
240 IF A$ = "M" THEN PLAY "O4A"
250 IF A$=" , " THEN PLAY "O4B" 260 IF A$=" . " THEN PLAY "O5C"
27Ø IF A$=" / " THEN PLAY "O5D"
280 IF A$ = "A" THEN PLAY "O3B - "
290 IF A$ = "D" THEN PLAY "O4C +"
300 IF A$ = " F" THEN PLAY "O4D +"
310 IF A$ = "H" THEN PLAY "O4F +"
320 IF A$ = " J " THEN PLAY "O4G +"
330 IF A$ = " K " THEN PLAY "O4A + "
340 IF A$=";" THEN PLAY "O5C+"
35Ø GOTO 17Ø
36Ø END
```

To stop the program, press $\boxed{\text{CTRL}} + \boxed{\text{STOP}}$. (Press the keys in the uppercase mode.)

* The graphic symbols in lines 50 to 150 are only included to make the screen more readable, and may be omitted.

Sample 3


```
10 REM ANIMATION
20 SCREEN 2, 1
3Ø COLOR 15, 1, 1:CLS
40 LINE ( 0, 114) - (255, 114), 2
50 PAINT (50, 130), 2
60 LINE ( 10, 50) - ( 60, 114), 10, BF
70 LINE ( 60, 114) - (110, 70), 9, BF
80 LINE (110, 40) - (160, 114), 13, BF
90 LINE (160, 114) - (200, 60), 12, BF
100 LINE (200, 30) - (255, 114), 14, BF
110 FOR I = 1 TO 10
120 READ X, Y, X1, Y1
130 LINE (X, Y)-(X1, Y1), 1, BF
140 NEXT I
15Ø FOR I=1 TO 8
160 READ A:A=A+CHR(A)
170 NEXT I
18Ø FOR I = 1 TO 8
190 READ B:B\$ = B\$ + CHR\$(B)
200 NEXT I
210 FOR I = 1 TO 8
220 READ C:C\$ = C\$ + CHR\$(C)
230 NEXT I
24\emptyset SPRITE$(\emptyset) = A$
250 SPRITE(1) = B$
260 \text{ SPRITE}(2) = C$
270 X = 0:Y = 100
280 PLAY "S13M150F A F A F A F A F A F A"
290 PUT SPRITE Ø, (X, Y), 8, Ø
300 PUT SPRITE 1, (X, Y), 1, 1
310 PUT SPRITE 2, (X, Y), 15, 2
320 X = X + 1
330 IF X>255 THEN X = 0 ELSE 290
34Ø GOTO 28Ø
35Ø END
```


```
360 DATA 15, 60, 30, 80, 40, 60, 55, 80
370 DATA 65, 75, 75, 85, 80, 75, 90, 85
380 DATA 95, 75, 105, 85, 120, 50, 150, 60
390 DATA 120, 70, 150, 80, 165,
                              70, 175,
                                       80
400 DATA 185,
              70, 195, 80, 210, 40, 245,
                                       50
               Ø, 32, 112, 32,
410 DATA 16,
                               Ø,
                                   Ø,
                                        Ø
420 DATA
           Ø,
              Ø, 4, Ø, Ø,
                               Ø, 68,
430 DATA
           0, 252, 216, 143, 233, 255,
```

When RUN is input, an ambulance runs across the screen from left to right while sounding its siren. To stop the program, press [CTRL] + [STOP].


Design Sheets

Text Screen Design Sheets







Graphic Screen Design Sheets



Sprite Design Sheets (8×8)



Sprite Design Sheets (16×16)



INDEX

AUTO	10
BEEP	88
CHR\$	44
CIRCLE	
CLS	
COLOR	52
CONT	
DELETE	16
DRAW	67
END	9
FOR ~ NEXT	29
GOSUB ~ RETURN	
GOTO	24
IF ~ THEN	
IF ~ THEN ~ ELSE	
INT	46
INKEY\$	47
INPUT	31
KEY	11
LINE	57
LIST	
LOCATE	22
NEW	9
ON SPRITE GOSUB	83
PAINT	59
PLAY	89
PRINT	18
PRESET	
PSET	65
PUT SPRITE	
READ ~ DATA	38
REM	8
RENUM	15
RESTORE	
RND	46
RUN	
SCREEN 50,	57
SPRITE ON/OFF/STOP	
SPRITE\$	75
	27



